

My Project

Generated by Doxygen 1.9.1

1 Hierarchical Index	1
1.1 Class Hierarchy	1
2 Class Index	3
2.1 Class List	3
3 Class Documentation	5
3.1 BufferWriter Class Reference	5
3.2 DetectionResult Struct Reference	5
3.3 ExperimentConfig Class Reference	6
3.4 ExperimentRuntime Class Reference	6
3.5 GCC_Value_Error Class Reference	7
3.6 ONNXModel Class Reference	7
3.7 Session Class Reference	8
3.8 SocketManager Class Reference	8
3.8.1 Member Function Documentation	8
3.8.1.1 RestartListener()	8
Index	9

Chapter 1

Hierarchical Index

1.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

BufferWriter	5
DetectionResult	5
ExperimentConfig	6
ExperimentRuntime	6
ONNXModel	7
std::runtime_error	
GCC_Value_Error	7
Session	8
SocketManager	8

Chapter 2

Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

BufferWriter	5
DetectionResult	5
ExperimentConfig	6
ExperimentRuntime	6
GCC_Value_Error	7
ONNXModel	7
Session	8
SocketManager	8

Chapter 3

Class Documentation

3.1 BufferWriter Class Reference

Public Member Functions

- void **write** (std::vector< Eigen::VectorXf > &buffer, std::vector< std::chrono::system_clock::time_point > &peakTimesBuffer, const std::string &outputFile)

Public Attributes

- std::chrono::milliseconds **_flushInterval**
- size_t **_bufferSizeThreshold**
- std::chrono::time_point< std::chrono::steady_clock > **_lastFlushTime**

The documentation for this class was generated from the following file:

- C/src/buffer_writer.h

3.2 DetectionResult Struct Reference

Public Attributes

- int **minPeakIndex** = -1
- int **maxPeakIndex** = -1
- std::chrono::system_clock::time_point **peakTimes**
- float **peakAmplitude**

The documentation for this struct was generated from the following file:

- C/src/process_data.h

3.3 ExperimentConfig Class Reference

Public Attributes

- `const std::function< void(std::span< float >, Eigen::MatrixXf &, unsigned int)> ProcessFncPtr = Process↵
SegmentInterleaved`
- `std::unique_ptr< ONNXModel > onnxModel`

Static Public Attributes

- `static constexpr int HEAD_SIZE = 12`
- `static constexpr int NUM_CHAN = 4`
- `static constexpr int SAMPS_PER_CHANNEL = 124`
- `static constexpr int BYTES_PER_SAMP = 2`
- `static constexpr int MICRO_INCR = 1240`
- `static constexpr int SAMPLE_RATE = 1e5`
- `static constexpr int DATA_SIZE = SAMPS_PER_CHANNEL * NUM_CHAN * BYTES_PER_SAMP`
- `static constexpr int PACKET_SIZE = DATA_SIZE + HEAD_SIZE`
- `static constexpr int REQUIRED_BYTES = DATA_SIZE + HEAD_SIZE`
- `static constexpr int DATA_BYTES_PER_CHANNEL = SAMPS_PER_CHANNEL * BYTES_PER_SAMP`
- `static constexpr float TIME_WINDOW = 0.01`
- `static constexpr int NUM_PACKS_DETECT = static_cast<int>(TIME_WINDOW * 100000 / SAMPS_PER↵
_CHANNEL)`
- `static constexpr int DATA_SEGMENT_LENGTH = NUM_PACKS_DETECT * SAMPS_PER_CHANNEL *
NUM_CHAN`
- `static constexpr float speedOfSound = 1482.965459`
- `static constexpr int interp = 1`
- `static constexpr const char * filterWeights = "filters/highpass_taps@101_cutoff@20k_window@hamming↵
_fs@100k.txt"`
- `static constexpr const char * receiverPositions = "../Data/SOCAL_H_72_HS_harp4chPar_recPos.txt"`
- `static constexpr const char * onnxModelPath = "../TestOnnx/model_quantized_static.onnx"`
- `static constexpr const char * onnxModelScaling = "../TestOnnx/scaler_params.json"`

The documentation for this class was generated from the following file:

- `C/src/custom_types.h`

3.4 ExperimentRuntime Class Reference

Public Attributes


- `std::string detectionOutputFile = ""`
- `std::chrono::seconds programRuntime`
- `TimePoint programStartTime`
- `float energyDetThresh = 100.0f`
- `fftwf_plan forwardFFT = nullptr`
- `fftwf_plan inverseFFT = nullptr`

The documentation for this class was generated from the following file:


- `C/src/custom_types.h`

3.5 GCC_Value_Error Class Reference

Inheritance diagram for GCC_Value_Error:



Collaboration diagram for GCC_Value_Error:



Public Member Functions

- **GCC_Value_Error** (const std::string &message)

The documentation for this class was generated from the following file:

- C/src/custom_types.h

3.6 ONNXModel Class Reference

Public Member Functions

- **ONNXModel** (const std::string &model_path, const std::string &scaler_params_path)
- std::vector< int64_t > **get_input_node_info** ()
- void **load_scaler_params** (const std::string &file_path)
- std::vector< float > **run_inference** (const std::vector< float > &input_tensor_values)
- void **normalize_data** (std::vector< float > &data) const

The documentation for this class was generated from the following file:

- C/src/onnx_model.h

3.7 Session Class Reference

Public Member Functions

- int **pushDataToBuffer** (const std::vector< uint8_t > &data)
- std::vector< uint8_t > **popDataFromBuffer** ()

Public Attributes

- std::atomic< bool > **errorOccurred** = false
- std::queue< std::vector< uint8_t > > **dataBuffer**
- std::vector< std::vector< uint8_t > > **dataBytesSaved**
- std::vector< float > **dataSegment**
- std::vector< std::chrono::system_clock::time_point > **dataTimes**
- std::mutex **dataBufferLock**
- int **detectionCounter** = 0
- std::vector< Eigen::VectorXf > **Buffer**
- std::vector< std::chrono::system_clock::time_point > **peakTimesBuffer**

The documentation for this class was generated from the following file:

- C/src/session.h

3.8 SocketManager Class Reference

Public Member Functions

- void [RestartListener](#) ()

Public Attributes

- int **datagramSocket** = socket(AF_INET, SOCK_DGRAM, 0)
- int **UDP_PORT**
- std::string **UDP_IP**

3.8.1 Member Function Documentation

3.8.1.1 RestartListener()

```
void SocketManager::RestartListener ( ) [inline]
```

(Re)starts the udp listener. It closes the existing socket connection and creates a new one. Additionally, it clears the buffer (dataBuffer) and the segment to be processed (dataSegment) as well as the vector containing the timestamps (dataTimes).

The documentation for this class was generated from the following file:

- C/src/socket_manager.h

Index

BufferWriter, [5](#)

DetectionResult, [5](#)

ExperimentConfig, [6](#)

ExperimentRuntime, [6](#)

GCC_Value_Error, [7](#)

ONNXModel, [7](#)

RestartListener

- SocketManager, [8](#)

Session, [8](#)

SocketManager, [8](#)

- RestartListener, [8](#)